

# Parallelism and Concurrency (Again)

We're done talking about parallelism. Our goal is no longer (necessarily) "to make the program faster".

The  ${\tt ForkJoin}$  Framework is great, but it doesn't actually allow us to share resources.

Two threads only interact at birth and death

For the next few lectures, we'll investigate what happens when we lift that restriction.

Two threads can run different algorithms now

# Why Use Threads Then?

- Code structure for responsiveness
  - Example: Respond to GUI events in one thread while another thread is performing an expensive computation
- Processor utilization (mask I/O latency)
  - If 1 thread goes to disk, have something else to do
- Failure isolation
  - Convenient structure if want to interleave multiple tasks and do not want an exception in one to stop the other

# Very Complicated, Very Quickly...

Concurrent code gets very complicated very quickly. Why?

#### Concurrency introduces non-determinism!


In sequential programming, when you run the same program multiple times, you get the same result (Random isn't really random; it just uses a  $\ensuremath{\texttt{seed}}$ ).

This is no longer true for concurrent programs:

Thread 0	Thread 1
print("Hi I'm Thread O");	<pre>print("Hi I'm Thread 1");</pre>
Thread 2	Thread 3
print("Hi I'm Thread 2");	print("Hi I'm Thread 3");

These threads could run in any order...

estigating How Things Can	Go Wrong
Concurrent code is only correct if a	all possible executions are correct.
Store	
Store.ca	sh = 1000;
Customer1.wallet = 100;	Customer2.wallet = 200;
Customer 1	Customer 2
<pre>int store = Store.cash + 50;</pre>	<pre>int store = Store.cash + 20;</pre>
Customer1.wallet -= 50;	<pre>2 Customer2.wallet -= 20;</pre>
Customer1.wallet -= 50;	<pre>2 Customer2.wallet -= 20;</pre>
Customer1.wallet -= 50; Store.cash = store;	Customer2.wallet -= 20; Store.cash = store;
Customer1.wallet -= 50; Store.cash = store; What Happens With This Interleav	Customer2.wallet -= 20; Store.cash = store;
Customer1.wallet -= 50; Store.cash = store;	Customer2.wallet -= 20; Store.cash = store;
Customer1.wallet -= 50; Store.cash = store; What Happens With This Interleav	Customer2.wallet -= 20; Store.cash = store; ing? int store = Store.cash + 20;
Customer1.wallet -= 50; Store.cash = store; What Happens With This Interleav int store = Store.cash + 50;	Customer2.wallet -= 20; Store.cash = store;
Customer1.wallet -= 50; Store.cash = store; What Happens With This Interleav	Customer2.wallet -= 20; Store.cash = store; ing? int store = Store.cash + 20;



The compiler is allowed to re-order lines 1 and 2 on the left.

To fix it, we insist that lines 1 and 2 happen together. We'll see how to do this later today.

## **Data Races**

#### Definition (Data Race)

When two threads interact such that:

- One of them writes to a variable x
- And the other reads from or writes to the same variable x
- Data Races can be a problem for two reasons:
- **I** They can lead to race conditions (we'll talk about this case)
- The compiler/CPU is allowed to re-order the reads/writes which causes errors (we'll ignore this)

Note that two reads from the same variable is not a data race.

To fix a data race, we insist that the relevant reads/writes are **atomic** (must happen together).

For the remainder of the course, we will assume that the compiler **does not** re-order lines, but you must avoid data races in practice.

8

# **Back To Race Conditions**

## Definition (Race Condition)

A race condition is a concurrency bug that causes the result of the computation to depend on the interleaving of threads. In other words, a program has a race condition if **any** interleaving of instructions in threads results in an incorrect computation.

The result of the store example should be Store.cash = 170, but if we look at the interleaving from before:

<pre>int store = Store.cash + 50;</pre>	
	<pre>int store = Store.cash + 20;</pre>
	Customer2.wallet -= 20;
Customer1.wallet -= 50;	
	<pre>Store.cash = store;</pre>
<pre>Store.cash = store;</pre>	

 ${\tt Store.cash}$  will end up equaling 150. Are there any other interleavings that lead to different results?

So, what's the solution?

#### How Do We Get Mutual Exclusion?

We need to make use of a language feature to do this. (If you take CSE451, you will implement your own mutexes.)

#### Definition (Mutex (Lock))

A **mutex** is a way of marking a critical section. If one thread "has the lock", all other threads wait to get the lock before entering the critical section.

We define Lock as an ADT:

### Lock ADT

new()	Creates a new lock which no thread holds
lock()	If the lock is not held by any threads, then the calling thread acquires it. Otherwise, the thread waits until the lock is free.
unlock()	If the lock is held by this thread, the calling thread releases it. Otherwise, calling this method is an error.


#### Atomicity

9


Store.cash changed between reading and writing!


We want **only one thread** to be able to be working with a value of Store.cash at a time. (Or we might get a stale value like above)

When there is a section of code that must occur **atomically** to avoid race conditions, we call this a **critical section**.



The idea of only allowing one thread in the critical section at a time is called **mutual exclusion**.







It does! Notice that both threads reading input is okay!


The problem is that they're both writing to sum.


We could put a mutex around each for loop, but we can do better:





And Aga			1
1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 Do we	<pre>Lock lock = new Lock(); void push(E val) { lock.lock(); array[++index] = val; lock.unlock(); } E pop() { lock.lock(); array[index] = val; lock.unlock(); } E peek() { return array[index]; }</pre>		
int	newIndex = ++index;		
		<pre>return array[index];</pre>	
arra	y[newIndex] = val;		





# 13

E ans = s.pop();	
	s.push(5);
s.push(ans);	
return ans;	
	s.pop();

In this interleaving, the top two elements end up in the wrong order!

Notice that with our definition of locks, we can't just fix this problem by putting lock around the contents of peek even though that seems like a reasonable solution.


To fix this, we'd need to make private versions of  $\operatorname{push}$  and  $\operatorname{pop}$  that don't lock and use those.

#### A Note: Reentrant Locks

**ANOTHER Example!** 


A reentrant lock is a mutex that can be taken multiple times by the same thread.


A reentrant lock would also solve our problem.



These stupid threads are waiting for each other!


This is called deadlock.






1	class BankAccount {		
2	Lock lock = <b>new</b> Lock(); <b>void</b> withdraw( <b>int</b> amt) {		
3	this.lock.lock();		
5	thiswithdraw(amt);	Assume that _withdraw and	
6	this.lock.unlock():	_	
7	}	_deposit are the unlocked versions.	
8	<pre>void deposit(int amt) {</pre>		
9	<pre>this.lock.lock();</pre>		
10	<pre>thisdeposit(amt);</pre>	Consider two simultaneous transfers:	
11	<pre>this.lock.unlock();</pre>	Consider two simultaneous transfers:	
12	}		
13	void transfer(int amt, BankAccount		
14	<pre>b) { this.lock.lock():</pre>	a.transfer(100, b);	
14 15	thiswithdraw(amt);	<pre>b.transfer(100, a);</pre>	
15	b.deposit(amt);	<b>D</b> : Clamsfel (100, a),	
17	this.lock.unlock();		
18	}		
19	}		
	Do you see	any problems?	


a.lock.lock();		
	<pre>b.lock.lock();</pre>	
awithdraw(amt);		
	<pre>bwithdraw(amt);</pre>	
b.lock.lock();		
	a.lock.lock();	
bdeposit(amt);		
	adeposit(amt);	
b.lock.unlock();		
	a.lock.unlock();	
a.lock.unlock();		
	b.lock.unlock();	



- Solution 2: Make a special mutex for "all transfers" Bad because it doesn't allow multiple transfers at once.
- Solution 3: Order the locks (like with Dining Philosophers)



## Okay, Race Conditions and Deadlock Suck...



## **Thread-Local Memory**

#### Definition (Thread-Local Memory)

**Thread-Local Memory** is only used by a single thread. All the instance variables in the RecursiveTasks we've been writing are Thread-Local Memory.

If a thread has its own  $\mbox{copy}$  of a resource, then we don't have to worry about other threads updating it.

This only works if the threads don't need to share the resource.

#### Example

- Random Objects don't need to be shared
- In p3, you will make a copy of the Board object for each thread to work with.

#### Immutable Memory

25

27

23

#### Definition (Immutable Memory)

**Immutable Memory** is memory that never changes. All the **input** arrays we've been passing to RecursiveTasks have been Immutable Memory.

If none of the threads write to the location, then they can all share the same  $\operatorname{copy}!$ 

#### Example

- Generally, input data structures won't be mutated.
- In p3, you will share Move objects between threads (since they never change).

# What's Left? If it's not possible to use Thread-Local Memory or Immutable Memory for a task, we're stuck with using synchronization. Try as much as possible to minimize this category If we must use synchronization, ... Guideline #0: Avoid Data Races Never allow two threads to write/write or read/write to the same location at the same time. (Avoid this with mutexes.) Guideline #1: Use Consistent Locking For each location needing synchronization, have a lock that is always held when reading or writing the location. ■ Use the same lock to guard multiple locations when it makes sense ■ Clearly document what each lock is for ■ Conceptually partition shared-and-mutable locations into "which lock"

But how much should each lock be responsible for?

#### Lock Granularity

#### Guideline #2: Start With Fewer Locks

Start with fewer locks (coarse-grained) and move to more (fine-grained) only if contention on the locks becomes an issue.

#### Definition (Coarse-Grained)

Fewer Locks (more objects/lock)

- Lock for entire data structure (e.g., array)
- Lock for all bank accounts

#### Coarse-Grained Advantages

- Simpler to implement
   Faster/easier to implement operations that access multiple locations
- Much easier for operations that modify data-structure shape

#### Definition (Fine-Grained)

- More Locks (fewer objects/lock)
  - Lock per data element (e.g., array index)
  - Lock per bank account

# Fine-Grained Advantages

 More simultaneous access
 Can make multi-node operations more difficult: say, rotations in an AVL tree

## Lock Granularity Example: Separate Chaining Hashtable 28

Lock for entire hashtable (coarse) vs. Lock per bucket (fine)

- Which supports more concurrency for insert and lookup? Fine-grained; allows simultaneous access to different buckets
- Which makes implementing resize easier? Coarse-grained; just grab one lock and proceed
- If a hashtable has a numElements field, maintaining it will destroy the benefits of using separate locks for each bucket, why? Updating it each insert without a lock would be a data race

#### 24

26

## **Critical Section Granularity**

# 29

## Guideline #3: Keep Critical Sections Small

Don't do expensive computations or I/O in critical sections, but also don't introduce race conditions. In other words, keep critical sections as small as possible without being incorrect.

- If critical sections are too long, it's a huge performance loss.
- If critical sections are too short, we get race conditions (visible intermediary state).

# Atomicity & Libraries

#### Guideline #4: Think About Atomicity

Think in terms of what operations need to be atomic and make critical sections just long enough to preserve atomicity. Then, design the locking protocol to implement the critical sections correctly.

#### Guideline #5: Use Libraries

Avoid implementing data structure synchronization as much as possible. Most languages have built-in libraries to handle frequent needs.

For example, ConcurrentHashMap is written by world-experts who know what they are doing. It would be silly to write your own.

#### Some Final Words on Synchronization 31 Java has a special syntax called synchronized for locking: Our Code In Java 1 method() { 1 method() { 2 lock.lock(); 2 synchronized(this) { 3 doStuff(); lock.unlock(); 3 doStuff(); 4 5 } } 4 5 } This code treats the actual object as the lock. Other Synchronization Primitives Condition Variables have signal and wait methods. wait allows a thread to wait until some condition is true. signal wakes the

- thread up at the right time.
  Reader-Writer Locks allow threads to declare if they are reading or writing to a resource. These allow multiple readers at the same time.
- ... and others.