

# Machine Language

---

- Today we'll discuss machine language, the binary representation for instructions.
  - We'll see how it is **designed for the common case**
    - Fixed-sized (32-bit) instructions
    - Only 3 instruction formats
    - Limited-sized immediate fields

## Assembly vs. machine language

---

- So far we've been using **assembly language**.
  - We assign names to operations (e.g., **add**) and operands (e.g., **\$t0**).
  - Branches and jumps use labels instead of actual addresses.
  - Assemblers support many pseudo-instructions.
- Programs must eventually be translated into **machine language**, a binary format that can be stored in memory and decoded by the CPU.
- MIPS machine language is designed to be easy to decode.
  - Each MIPS instruction is the same length, 32 bits.
  - There are only three different instruction formats, which are very similar to each other.
- Studying MIPS machine language will also reveal some restrictions in the instruction set architecture, and how they can be overcome.

## R-type format

---

- Register-to-register arithmetic instructions use the **R-type** format.



- This format includes six different fields.
  - **op** is an **operation code** or **opcode** that selects a specific operation.
  - **rs** and **rt** are the first and second source registers.
  - **rd** is the destination register.
  - **shamt** is only used for shift instructions.
  - **func** is used together with **op** to select an arithmetic instruction.
- The inside back cover of the textbook lists opcodes and function codes for all of the MIPS instructions.

## About the registers

---

- We have to encode register names as 5-bit numbers from 00000 to 11111
  - For example, **\$t8** is register \$24, which is represented as **11000**.
  - The complete mapping is given on page A-23 in the book.
- The number of registers available affects the instruction length.
  - Each R-type instruction references 3 registers, which requires a total of 15 bits in the instruction word.
  - We can't add more registers without either making instructions longer than 32 bits, or shortening other fields like **op** and possibly reducing the number of available operations.



## I-type format

---

- Load, store, branch and immediate instructions all use the **I-type** format.



- For uniformity, **op**, **rs** and **rt** are in the same positions as in the R-format.
- The meaning of the register fields depends on the exact instruction.
  - **rs** is a source register—an address for loads and stores, or an operand for branch and immediate arithmetic instructions.
  - **rt** is a source register for branches, but a destination register for the other I-type instructions.
- The **address** is a 16-bit signed two's-complement value.
  - It can range from -32,768 to +32,767.
  - But that's not always enough!

## Larger constants

---

- Larger constants can be loaded into a register 16 bits at a time.
  - The load upper immediate instruction **lui** loads the highest 16 bits of register with a constant, and clears the lowest 16 bits to 0s.
  - An immediate logical OR, **ori**, then sets the lower 16 bits.
- To load the 32-bit value 0000 0000 0011 1101 0000 1001 0000 0000:

```
lui $s0, 0x003D          # $s0 = 003D 0000 (in hex)
ori $s0, $s0, 0x0900     # $s0 = 003D 0900
```

- This illustrates the principle of making the common case fast.
  - Most of the time, 16-bit constants are enough.
  - It's still possible to load 32-bit constants, but at the cost of two instructions and one temporary register.
- Pseudo-instructions may contain large constants. Assemblers including SPIM will translate such instructions correctly.

## Loads and stores

---

- The limited 16-bit constant can present problems for accesses to global data.
- Suppose we want to load from address 0x10010004.

```
lui   $at, 0x1001           # 0x1001 0000
lw    $t1, 0x0004($at)     # Read from Mem[0x1001 0004]
```


## Branches

---

- For branch instructions, the constant field is not an address, but an *offset* from the current program counter (PC) to the target address.

```
beq   $at, $0, L
add   $v1, $v0, $0
add   $v1, $v1, $v1
j     Somewhere
L:    add   $v1, $v0, $v0
```

- Since the branch target `L` is three *instructions* past the `beq`, the address field would contain 3. The whole `beq` instruction would be stored as:



- For some reason SPIM is off by one, so the code it produces would contain an address of 4. (But SPIM branches still execute correctly.)

## Larger branch constants

---

- Empirical studies of real programs show that most branches go to targets less than 32,767 instructions away—branches are mostly used in loops and conditionals, and programmers are taught to make code bodies short.
- If you do need to branch further, you can use a jump with a branch. For example, if “Far” is very far away, then the effect of:

```
beq $s0, $s1, Far
...
```

can be simulated with the following actual code.


```
       bne $s0, $s1, Next
Next:  j     Far
       ...
```

- Again, the MIPS designers have taken care of the common case first.

## J-type format

---

- Finally, the jump instruction uses the **J-type** instruction format.



- The jump instruction contains a *word* address, **not an offset**
  - Remember that each MIPS instruction is one word long, and word addresses must be divisible by four.
  - So instead of saying “jump to address 4000,” it’s enough to just say “jump to instruction 1000.”
  - A 26-bit address field lets you jump to any address from 0 to  $2^{28}$ .
    - your MP solutions had better be smaller than 256MB
- For even longer jumps, the jump register, or **jr**, instruction can be used.

**jr** \$ra # Jump to 32-bit address in register \$ra

## Summary

---

- Machine language is the binary representation of instructions:
  - The format in which the machine actually executes them
- MIPS machine language is designed to simplify processor implementation
  - Fixed length instructions
  - 3 instruction encodings: R-type, I-type, and J-type
  - Common operations fit in 1 instruction
    - Uncommon (e.g., long immediates) require more than one