


CSE 451: Operating Systems  
Winter 2006

Module 12  
Page Table Management, TLBs,  
and Other Pragmatics

Ed Lazowska  
lazowska@cs.washington.edu  
Allen Center 570

Address translation and page faults  
(refresher!)



2/17/2006

© 2006 Gribble, Lazowska, Levy

2

How does OS handle a page fault?

- Interrupt causes system to be entered
- System saves state of running process, then vectors to page fault handler routine
  - find or create (through eviction) a page frame into which to load the needed page (1)
    - if I/O is required, run some other process while it's going on
  - find the needed page on disk and bring it into the page frame (2)
    - run some other process while the I/O is going on
  - fix up the page table entry
    - mark it as "valid," set "referenced" and "modified" bits to false, set protection bits appropriately, point to correct page frame
  - put the process on the ready queue

2/17/2006

© 2006 Gribble, Lazowska, Levy

3

- (2) Find the needed page on disk and bring it into the page frame
  - processor makes process ID and faulting virtual address available to page fault handler
  - process ID gets you to the base of the page table
  - VPN portion of VA gets you to the PTE
  - data structure analogous to page table (an array with an entry for each page in the address space) contains disk address of page
  - at this point, it's just a simple matter of I/O
    - must be positive that the target page frame remains available!
      - or what?

2/17/2006

© 2006 Gribble, Lazowska, Levy

4

- (1) Find or create (through eviction) a page frame into which to load the needed page

- run page replacement algorithm
  - free page frame
  - assigned but unmodified ("clean") page frame
  - assigned and modified ("dirty") page frame
- assigned but "clean"
  - find PTE (may be a different process!)
  - mark as invalid (disk address must be available for subsequent reload)
- assigned and "dirty"
  - find PTE (may be a different process!)
  - mark as invalid
  - write it out

2/17/2006

© 2006 Gribble, Lazowska, Levy

5

"Issues"

- Memory reference overhead of address translation
  - 2 references per address lookup (page table, then memory)
  - solution: use a hardware cache to absorb page table lookups
    - translation lookaside buffer (TLB)
- Memory required to hold page tables can be huge
  - need one PTE per page in the virtual address space
  - 32 bit AS with 4KB pages =  $2^{20}$  PTEs = 1,048,576 PTEs
  - 4 bytes/PTE = 4MB per page table
    - OS's typically have separate page tables per process
    - 25 processes = 100MB of page tables
  - 48 bit AS, same assumptions, 64GB per page table!
  - solution: page the page tables!
    - (ow, my brain hurts ...)

2/17/2006

© 2006 Gribble, Lazowska, Levy

6

## Paging the page tables 1

- Simplest notion:
  - put user page tables in a pageable segment of the system's address space
  - wire down the system's page table(s) in physical memory
  - allow the system segment containing the user page tables to be paged
    - a reference to a non-resident portion of a user page table is a page fault in the system address space
    - the system's page table is wired down
      - "no smoke and mirrors"
- As a practical matter, this simple notion doesn't cut the mustard today
  - although it is *exactly* what VAX/VMS did!
- But it's a useful model for what's actually done

2/17/2006

© 2006 Gribble, Lazowska, Levy

7

## Paging the page tables 2

- How can we reduce the physical memory requirements of page tables?
  - observation: only need to map the portion of the address space that is actually being used (often a tiny fraction of the total address space)
    - a process may not use its full 32/48/64-bit address space
    - a process may have unused "holes" in its address space
    - a process may not reference some parts of its address space for extended periods
  - all problems in CS can be solved with a level of indirection!
    - two-level (three-level, four-level) page tables

2/17/2006

© 2006 Gribble, Lazowska, Levy

8

## Two-level page tables


- With two-level PT's, virtual addresses have 3 parts:
  - master page number, secondary page number, offset
  - master PT maps master PN to secondary PT
  - secondary PT maps secondary PN to page frame number
  - offset and PFN yield physical address

2/17/2006

© 2006 Gribble, Lazowska, Levy

9

## Two level page tables



2/17/2006

© 2006 Gribble, Lazowska, Levy

10

- Example:
  - 32-bit address space, 4KB pages, 4 bytes/PTE
    - how many bits in offset?
      - need 12 bits for 4KB ( $2^{12}=4K$ ), so offset is 12 bits
    - want master PT to fit in one page
      - 4KB/4 bytes = 1024 PTEs
      - thus master page # is 10 bits ( $2^{10}=1K$ )
      - and there are 1024 secondary page tables
    - and 10 bits are left ( $32-12-10$ ) for indexing each secondary page table
      - hence, each secondary page table has 1024 PTEs and fits in one page

2/17/2006

© 2006 Gribble, Lazowska, Levy

11

## Generalizing

- Early architectures used 1-level page tables
- VAX, P-II used 2-level page tables
- SPARC uses 3-level page tables
- 68030 uses 4-level page tables
- Key thing is that the outer level must be **wired down** (pinned in physical memory) in order to break the recursion – *no smoke and mirrors*

2/17/2006

© 2006 Gribble, Lazowska, Levy

12

## Alternatives

- Hashed page table (great for sparse address spaces)
  - VPN is used as a hash
  - collisions are resolved because the elements in the linked list at the hash index include the VPN as well as the PFN
- Inverted page table (really reduces space!)
  - one entry per page frame
  - includes process id, VPN
  - hell to search! (but IBM PC/RT actually did this!)

2/17/2006

© 2006 Gribble, Lazowska, Levy

13

## Making it all efficient

- Original page table scheme doubled the cost of memory lookups
  - one lookup into page table, a second to fetch the data
- Two-level page tables triple the cost!!
  - two lookups into page table, a third to fetch the data
- How can we make this more efficient?
  - goal: make fetching from a virtual address about as efficient as fetching from a physical address
  - solution: use a hardware cache inside the CPU
    - cache the virtual-to-physical translations in the hardware
    - called a **translation lookaside buffer (TLB)**
    - TLB is managed by the memory management unit (MMU)

2/17/2006

© 2006 Gribble, Lazowska, Levy

14

## TLBs

- Translation lookaside buffer
  - translates virtual page #s into PTEs (page frame numbers) (**not physical address**)
  - can be done in single machine cycle
- TLB is implemented in hardware
  - is a fully associative cache (all entries searched in parallel)
  - cache tags are virtual page numbers
  - cache values are PTEs (page frame numbers)
  - with PTE + offset, MMU can directly calculate the PA
- TLBs exploit locality
  - processes only use a handful of pages at a time
    - 16-48 entries in TLB is typical (64-192KB)
    - can hold the "hot set" or "working set" of a process
  - hit rates in the TLB are therefore really important

2/17/2006

© 2006 Gribble, Lazowska, Levy

15

## Managing TLBs

- Address translations are mostly handled by the TLB
  - >99% of translations, but there are **TLB misses** occasionally
  - in case of a miss, translation is placed into the TLB
- Hardware (memory management unit (MMU))
  - knows where page tables are in memory
    - OS maintains them, HW access them directly
  - tables have to be in HW-defined format
  - this is how x86 works
- Software loaded TLB (OS)
  - TLB miss faults to OS, OS finds right PTE and loads TLB
  - must be fast (but, 20-200 cycles typically)
    - CPU ISA has instructions for TLB manipulation
    - OS gets to pick the page table format

2/17/2006

© 2006 Gribble, Lazowska, Levy

16

## Managing TLBs (2)

- OS must ensure TLB and page tables are consistent
  - when OS changes protection bits in a PTE, it needs to invalidate the PTE if it is in the TLB
- What happens on a process context switch?
  - remember, each process typically has its own page tables
  - need to invalidate all the entries in TLB! (**flush TLB**)
    - **this is a big part of why process context switches are costly**
  - can you think of a hardware fix to this?
- When the TLB misses, and a new PTE is loaded, a cached PTE must be evicted
  - choosing a victim PTE is called the "TLB replacement policy"
  - implemented in hardware, usually simple (e.g., LRU)

2/17/2006

© 2006 Gribble, Lazowska, Levy

17

## Cool Paging Tricks

- Exploit level of indirection between VA and PA
  - shared memory
    - regions of two separate processes' address spaces map to the same physical frames
      - read/write: access to share data
      - execute: shared libraries!
    - will have separate PTEs per process, so can give different processes different access privileges
    - must the shared region map to the same VA in each process?
  - copy-on-write (COW), e.g., on fork( )
    - instead of copying all pages, created shared mappings of parent pages in child address space
      - make shared mappings read-only in child space
      - when child does a write, a protection fault occurs, OS takes over and can then copy the page and resume client

2/17/2006

© 2006 Gribble, Lazowska, Levy

18

- Memory-mapped files
  - instead of using open, read, write, close
    - “map” a file into a region of the virtual address space
      - e.g., into region with base ‘X’
    - accessing virtual address ‘X+N’ refers to offset ‘N’ in file
    - initially, all pages in mapped region marked as invalid
  - OS reads a page from file whenever invalid page accessed
  - OS writes a page to file when evicted from physical memory
    - only necessary if page is dirty

2/17/2006

© 2006 Gribble, Lazowska, Levy

19

## Summary

- We know how address translation works in the “vanilla” case (single-level page table, no fault, no TLB)
  - hardware splits the **virtual address** into the **virtual page number** and the **offset**; uses the VPN to index the **page table**; concatenates the offset to the **page frame number** (which is in the PTE) to obtain the physical address
- We know how the OS handles a page fault
  - find or create (through eviction) a page frame into which to load the needed page
  - find the needed page on disk and bring it into the page frame
  - fix up the page table entry
  - put the process on the ready queue

2/17/2006

© 2006 Gribble, Lazowska, Levy

20

- We’re aware of two “gotchas” that complicate things in practice
  - the memory reference overhead of address translation
    - the need to reference the page table doubles the memory traffic
    - solution: use a hardware cache (**TLB = translation lookaside buffer**) to absorb page table lookups
  - the memory required to hold page tables can be huge
    - solution: use **multi-level page tables**; can page the lower levels, or at least omit them if the address space is sparse
      - this makes the TLB even more important, because without it, a single user-level memory reference can cause two or three or four page table memory references ... and we can’t even afford one!

2/17/2006

© 2006 Gribble, Lazowska, Levy

21

- TLB details
  - Implemented in hardware
    - **fully associative cache** (all entries searched in parallel)
    - cache **tags** are virtual page numbers
    - cache **values** are page table entries (page frame numbers)
    - with PTE + offset, MMU can directly calculate the physical address
  - Can be small because of locality
    - 16-48 entries can yield a 99% hit ratio
  - Searched *before* the hardware walks the page table(s)
    - **hit**: address translation does not require an extra memory reference (or two or three or four) – “free”
    - **miss**: the hardware walks the page table(s) to translate the address; this translation is put into the TLB, evicting some other translation; typically managed LRU by the hardware

2/17/2006

© 2006 Gribble, Lazowska, Levy

22

- On context switch
  - TLB must be **purged/flushed** (using a special hardware instruction) unless entries are tagged with a process ID
    - otherwise, the new process will use the old process’s TLB entries and reference its page frames!
- Cool tricks
  - shared memory
  - copy-on-write
  - memory-mapped files

2/17/2006

© 2006 Gribble, Lazowska, Levy

23