#### CSE 451: Operating Systems Winter 2006

# Module 2 Architectural Support for Operating Systems

Ed Lazowska lazowska@cs.washington.edu 570 Allen Center

## Even coarse architectural trends impact tremendously the design of systems

- Processing power
  - doubling every 18 months
  - 60% improvement each year
  - factor of 100 every decade
  - 1980: 1 MHz Apple II+ == \$2,000
     1980 also 1 MIPS VAX-11/780 == \$120,000
  - 2005: 3.5GHz Pentium 4 == \$1,000



1/1/2006 © 2006 Gribble, Lazowska, Levv

- Aside: Where does it all go?
   Facetiously: "What Gordon giveth, Bill taketh away"
   Realistically: our expectations for what the system will do increase relentlessly
   e.g., GUI
   "Software is like a gas it expands to fill the available space" Nathan Myhrvold (1960-)

  Transistors Per Die

  \*\*Transistors Per Die\*\*

  \*\*Transisto

- Disk capacity, 1975-1989

  doubled every 3+ years

  25% improvement each year

  factor of 10 every decade

  Still exponential, but far less rapid than processor performance

  Disk capacity since 1990

  doubling every 12 months


  100% improvement each year

  factor of 1000 every decade

  10x as fast as processor performance!
- Only a few years ago, we purchased disks by the megabyte (and it hurt!)
  Today, 1 GB (a billion bytes) costs \$1 \$0.50 from Dell (except you have to buy in increments of 40 80 GB)

  = > 1 TB costs \$4 K \$500, 1 PB costs \$1 M \$500K
  In 3.2 years, 1 GB will cost \$.10


  = > 1 TB for \$100, 1 PB for \$100K













#### Storage Latency: How Far Away is the Data? Tape /Optical 2,000 Years Robot 10<sup>6</sup> Disk 2 Years 1.5 hr 100 Memory 10 On Board Cache On Chip Cache Registers Mv Head 1 min © 2004 Jim Gray, Microsoft Corporation

### Lower-level architecture affects the OS even more dramatically

- Operating system functionality is dictated, at least in part, by the underlying hardware architecture
  - includes instruction set (synchronization, I/O, ...)
  - also hardware components like MMU or DMA controllers
- Architectural support can vastly simplify (or complicate!) OS tasks
  - e.g.: early PC operating systems (DOS, MacOS) lacked support for virtual memory, in part because at that time PCs lacked necessary hardware support
    - Apollo workstation used two CPUs as a bandaid for nonrestartable instructions!
  - Most current Intel-based PCs still lack support for 64-bit addressing (which has been available for a decade on other platforms: MIPS, Alpha, IBM, etc...)
    - · changing rapidly due to AMD's new 64-bit architecture

1/1/2006

© 2006 Gribble, Lazowska, Levy

#### Architectural features affecting OS's

- These features were built primarily to support OS's:
  - timer (clock) operation
  - synchronization instructions (e.g., atomic test-and-set)
  - memory protection
  - I/O control operations
  - interrupts and exceptions
  - protected modes of execution (kernel vs. user)
  - protected instructions
  - system calls (and software interrupts)

1/1/2006

© 2006 Gribble, Lazowska, Levy

#### Protected instructions

- · some instructions are restricted to the OS
  - known as protected or privileged instructions
- . e.g., only the OS can:
  - directly access I/O devices (disks, network cards)
    - · why?
  - manipulate memory state management
  - page table pointers, TLB loads, etc.
  - why?
  - manipulate special 'mode bits'
    - interrupt priority level
  - why?
  - halt instruction
    - why?

1/1/2006

© 2006 Gribble, Lazowska, Levy

16

#### OS protection

- So how does the processor know if a protected instruction should be executed?
  - the architecture must support at least two modes of operation: kernel mode and user mode
    - VAX, x86 support 4 protection modes
  - mode is set by status bit in a protected processor register
    - user programs execute in user mode
    - OS executes in kernel mode (OS == kernel)
- Protected instructions can only be executed in kernel mode
  - what happens if user mode executes a protected instruction?

1/1/2006

© 2006 Gribble, Lazowska, Levy

17

15


#### Crossing protection boundaries

- So how do user programs do something privileged?
  - e.g., how can you write to a disk if you can't execute I/O instructions?
- User programs must call an OS procedure
  - OS defines a sequence of system calls
  - how does the user-mode to kernel-mode transition happen?
- There must be a system call instruction, which:
  - causes an exception (throws a software interrupt), which vectors to a kernel handler
  - passes a parameter indicating which system call to invoke
  - saves caller's state (regs, mode bit) so they can be restored
  - OS must verify caller's parameters (e.g., pointers)
  - must be a way to return to user mode once done

1/1/2006

© 2006 Gribble, Lazowska, Levy

3




#### System call issues

- What would happen if kernel didn't save state?
- · Why must the kernel verify arguments?
- How can you reference kernel objects as arguments or results to/from system calls?

1/1/2006 © 2006 Gribble, Lazowska, Levy 20

#### Memory protection

- OS must protect user programs from each other
  - maliciousness, ineptitude
- OS must also protect itself from user programs
  - integrity and security
  - what about protecting user programs from OS?
- Simplest scheme: base and limit registers
  - are these protected?



#### More sophisticated memory protection

- · coming later in the course
- · paging, segmentation, virtual memory
  - page tables, page table pointers
  - translation lookaside buffers (TLBs)
  - page fault handling

1/1/2006 © 2006 Gribble, Lazowska, Levy

22

24

#### OS control flow

- after the OS has booted, all entry to the kernel happens as the result of an event
  - event immediately stops current execution
  - changes mode to kernel mode, event handler is called
- · kernel defines handlers for each event type
  - specific types are defined by the architecture
    - e.g.: timer event, I/O interrupt, system call trap
  - when the processor receives an event of a given type, it
    - transfers control to handler within the OS
    - handler saves program state (PC, regs, etc.)
    - handler functionality is invoked
    - handler restores program state, returns to program

1/1/2006 © 2006 Gribble, Lazowska, Levy 23

#### Interrupts and exceptions

- Two main types of events: interrupts and exceptions
  - exceptions are caused by software executing instructions
    - e.g., the x86 'int' instruction
    - e.g., a page fault, or an attempted write to a read-only page
  - an expected exception is a "trap", unexpected is a "fault"
  - interrupts are caused by hardware devices
    - e.g., device finishes I/O
    - e.g., timer fires

1/1/2006 © 2006 Gribble, Lazowska, Levy

#### I/O control

- · Issues:
  - how does the kernel start an I/O?
    - special I/O instructions
    - memory-mapped I/O
  - how does the kernel notice an I/O has finished?
    - polling
    - interrupts
- Interrupts are basis for asynchronous I/O
  - device performs an operation asynchronously to CPU
  - device sends an interrupt signal on bus when done
  - in memory, a vector table contains list of addresses of kernel routines to handle various interrupt types
    - who populates the vector table, and when?
  - CPU switches to address indicated by vector index specified by interrupt signal

1/1/2006

© 2006 Gribble, Lazowska, Levy

27

#### **Timers**

- How can the OS prevent runaway user programs from hogging the CPU (infinite loops?)
  - use a hardware timer that generates a periodic interrupt
  - before it transfers to a user program, the OS loads the timer with a time to interrupt
    - "quantum" how big should it be set?
  - when timer fires, an interrupt transfers control back to OS
    - · at which point OS must decide which program to schedule next

26

28

- · very interesting policy question: we'll dedicate a class to it
- Should the timer be privileged?
  - for reading or for writing?

1/1/2006 © 2006 Gribble, Lazowska, Levy

#### Synchronization

- · Interrupts cause a wrinkle:
  - may occur any time, causing code to execute that interferes with code that was interrupted
  - OS must be able to synchronize concurrent processes
- Synchronization:
  - guarantee that short instruction sequences (e.g., read-
  - modify-write) execute atomically one method: turn off interrupts before the sequence, execute it, then re-enable interrupts
    - architecture must support disabling interrupts
  - another method: have special complex atomic instructions
    - · read-modify-write
    - · test-and-set
    - · load-linked store-conditional

1/1/2006

© 2006 Gribble Lazowska Levy

"Concurrent programming"

- · Management of concurrency and asynchronous events is biggest difference between "systems programming" and "traditional application programming"
  - modern "event-oriented" application programming is a middle ground
- · Arises from the architecture
- Can be sugar-coated, but cannot be totally abstracted away
- Huge intellectual challenge
  - Unlike vulnerabilities due to buffer overruns, which are just sloppy programming

1/1/2006

© 2006 Gribble Lazowska Levy