

# Virtual Memory I

CSE 351 Spring 2018









http://xkcd.com/292/

#### Roadmap

#### C:

```
car *c = malloc(sizeof(car));
c->miles = 100;
c->gals = 17;
float mpg = get_mpg(c);
free(c);
```

#### Java:

Memory & data
Integers & floats
x86 assembly
Procedures & stacks
Executables
Arrays & structs
Memory & caches
Processes

Virtual memory

Memory allocation Java vs. C

# Assembly language:

```
get_mpg:
    pushq %rbp
    movq %rsp, %rbp
    ...
    popq %rbp
    ret
```

# Machine code:


#### OS:








# Computer system:








# Virtual Memory (VM\*)

- Overview and motivation
- VM as a tool for caching
- Address translation
- VM as a tool for memory management
- VM as a tool for memory protection

**Warning:** Virtual memory is pretty complex, but crucial for understanding how processes work and for debugging performance


#### Memory as we know it so far... is virtual!

- Programs refer to virtual memory addresses
  - movq (%rdi),%rax
  - Conceptually memory is just a very large array of bytes
  - System provides private address space to each process
- Allocation: Compiler and run-time system
  - Where different program objects should be stored
  - All allocation within single virtual address space
- But...
  - We probably don't have 2<sup>w</sup> bytes of physical memory
  - We certainly don't have 2<sup>w</sup> bytes of physical memory for every process
  - Processes should not interfere with one another
    - Except in certain cases where they want to share code or data




CSE351, Spring 2018


# **Problem 1: How Does Everything Fit?**




#### **Problem 2: Memory Management**




#### **Problem 3: How To Protect**





#### **Problem 4: How To Share?**

#### Physical main memory



CSE351, Spring 2018

#### How can we solve these problems?

- Fitting a huge address space into a tiny physical memory
- 2) Managing the address spaces of multiple processes
- Protecting processes from stepping on each other's memory
- 4) Allowing processes to share common parts of memory

#### **Indirection**

\* "Any problem in computer science can be solved by adding another level of indirection." – David Wheeler, inventor of the subroutine

Without Indirection

P2

P3

NewThing

NewThing

NewThing

What if I want to move Thing?


#### **Indirection**

- Indirection: The ability to reference something using a name, reference, or container instead of the value itself. A flexible mapping between a name and a thing allows changing the thing without notifying holders of the name.
  - Adds some work (now have to look up 2 things instead of 1)
  - But don't have to track all uses of name/address (single source!)

#### Examples:

- Phone system: cell phone number portability
- Domain Name Service (DNS): translation from name to IP address
- Call centers: route calls to available operators, etc.
- Dynamic Host Configuration Protocol (DHCP): local network address assignment

#### Indirection in Virtual Memory



- Each process gets its own private virtual address space
- Solves the previous problems!


# **Address Spaces**

- \* Virtual address space: Set of  $N = 2^n$  virtual addr
  - {0, 1, 2, 3, ..., N-1}
- \* Physical address space: Set of  $M = 2^m$  physical addr
  - {0, 1, 2, 3, ..., M-1}

- Every byte in main memory has:
  - one physical address (PA)
  - zero, one, or more virtual addresses (VAs)


# Mapping

- A virtual address (VA) can be mapped to either physical memory or disk
  - Unused VAs may not have a mapping
  - VAs from different processes may map to same location in memory/disk




CSE351, Spring 2018

#### A System Using Physical Addressing



- Used in "simple" systems with (usually) just one process:
  - Embedded microcontrollers in devices like cars, elevators, and digital picture frames

#### A System Using Virtual Addressing




- Physical addresses are completely invisible to programs
  - Used in all modern desktops, laptops, servers, smartphones...
  - One of the great ideas in computer science

#### Why Virtual Memory (VM)?

- Efficient use of limited main memory (RAM)
  - Use RAM as a cache for the parts of a virtual address space
    - Some non-cached parts stored on disk
    - Some (unallocated) non-cached parts stored nowhere
  - Keep only active areas of virtual address space in memory
    - Transfer data back and forth as needed
- Simplifies memory management for programmers
  - Each process "gets" the same full, private linear address space
- Isolates address spaces (protection)
  - One process can't interfere with another's memory
    - They operate in *different address spaces*
  - User process cannot access privileged information
    - Different sections of address spaces have different permissions


#### VM and the Memory Hierarchy

- Think of virtual memory as array of  $N = 2^n$  contiguous bytes
- Pages of virtual memory are usually stored in physical memory, but sometimes spill to disk
  - Pages are another unit of aligned memory (size is  $P=2^p$  bytes)
  - Each virtual page can be stored in any physical page (no fragmentation!)



#### or: Virtual Memory as DRAM Cache for Disk


- \* Think of virtual memory as an array of  $N=2^n$  contiguous bytes stored on a disk
- Then physical main memory is used as a cache for the virtual memory array
  - These "cache blocks" are called *pages* (size is  $P = 2^p$  bytes)



CSE351, Spring 2018

#### **Memory Hierarchy: Core 2 Duo**

*Not drawn to scale* 



L20: Virtual Memory I

#### Virtual Memory Design Consequences

- Large page size: typically 4-8 KiB or 2-4 MiB
  - Can be up to 1 GiB (for "Big Data" apps on big computers)
  - Compared with 64-byte cache blocks
- Fully associative
  - Any virtual page can be placed in any physical page
  - Requires a "large" mapping function different from CPU caches
- Highly sophisticated, expensive replacement algorithms in OS
  - Too complicated and open-ended to be implemented in hardware
- Write-back rather than write-through
  - Really don't want to write to disk every time we modify something in memory
  - Some things may never end up on disk (e.g. stack for short-lived process)

#### Why does VM work on RAM/disk?


- Avoids disk accesses because of *locality*
  - Same reason that L1 / L2 / L3 caches work
- The set of virtual pages that a program is "actively" accessing at any point in time is called its working set
  - If (working set of one process ≤ physical memory):
    - Good performance for one process (after compulsory misses)
  - If (working sets of all processes > physical memory):
    - Thrashing: Performance meltdown where pages are swapped between memory and disk continuously (CPU always waiting or paging)
    - This is why your computer can feel faster when you add RAM

# Virtual Memory (VM)

- Overview and motivation
- VM as a tool for caching
- Address translation
- VM as a tool for memory management
- VM as a tool for memory protection

#### **Address Translation**

How do we perform the virtual → physical address translation?




#### **Address Translation: Page Tables**

CPU-generated address can be split into:


```
n-bit address: Virtual Page Number Page Offset
```

- Request is Virtual Address (VA), want Physical Address (PA)
- Note that Physical Offset = Virtual Offset (page-aligned)
- Use lookup table that we call the page table (PT)
  - Replace Virtual Page Number (VPN) for Physical Page Number (PPN) to generate Physical Address
  - Index PT using VPN: page table entry (PTE) stores the PPN plus management bits (e.g. Valid, Dirty, access rights)
  - [Conceptually] Has an entry for every virtual page why?

# Page Table Diagram




#### Page Table Address Translation




#### Page Hit

Page hit: VM reference is in physical memory



# Page Fault

Page fault: VM reference is NOT in physical memory




# Page Fault Exception

- User writes to memory location
- That portion (page) of user's memory is currently on disk


```
int a[1000];
int main ()
{
    a[500] = 13;
}
```

```
80483b7: c7 05 10 9d 04 08 0d movl $0xd,0x8049d10
```




- Page fault handler must load page into physical memory
- ❖ Returns to faulting instruction: mov is executed again!
  - Successful on second try


Page miss causes page fault (an exception)




- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)



- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)



- Page miss causes page fault (an exception)
- Page fault handler selects a victim to be evicted (here VP 4)
- Offending instruction is restarted: page hit!



#### **Peer Instruction Question**

- How many bits wide are the following fields?
  - 16 KiB pages
  - 48-bit virtual addresses
  - 16 GiB physical memory

	VPN	PPN
(A)	<b>34</b>	24
(B)	<b>32</b>	18
(C)	<b>30</b>	20
(D)	34	20

#### **Summary**

- Virtual memory provides:
  - Ability to use limited memory (RAM) across multiple processes
  - Illusion of contiguous virtual address space for each process
  - Protection and sharing amongst processes
- Indirection via address mapping by page tables
  - Part of memory management unit and stored in memory
  - Use virtual page number as index into lookup table that holds physical page number, disk address, or NULL (unallocated page)
  - On page fault, throw exception and move page from swap space (disk) to main memory