

# x86-64 Programming II

CSE 351 Summer 2020

## Instructor:

Porter Jones


## Teaching Assistants:

Amy Xu

Callum Walker

Sam Wolfson

Tim Mandzyuk



<http://xkcd.com/409/>

# Administrivia

- ❖ Questions doc: <https://tinyurl.com/CSE351-7-10>
- ❖ **See my email about accommodations!**
- ❖ Lab 1b now due Monday at 11:59pm (7/13)
  - Submit `aisle_manager.c`, `store_client.c`, and `lab1Breflect.txt`
  - Can still use late days until 7/15
- ❖ hw6, hw7 now due Monday (7/13) – 10:30am
- ❖ Unit Summary 1 now due Friday (7/17) – 11:59pm
  - Can still use late days until 7/20
- ❖ Mid-quarter Survey still due Friday (7/17) – 11:59pm
- ❖ hw8, hw9, hw10 now due Monday (7/20) – 10:30am

# Administrivia

- ❖ Lab1a grades released later today
  - Talk to us about any questions you have!
  - Regrades open 24 hours after an assignment is due, stay open usually for about a week
- ❖ Lab 2 released later today!
  - Debugging x86-64 assembly using gdb
- ❖ I will now drop your lowest homework score (see Syllabus for more details).
  - Essentially will bump your homework total up by 11.5 points (the largest single homework total).

# x86-64 Introduction

- ❖ Data transfer instruction (`mov`)
- ❖ Arithmetic operations
- ❖ **Memory addressing modes**
- ❖ **Address computation instruction (`lea`)**

# Memory Addressing Modes: Basic

❖ **Indirect:**  $(R)$   $\text{Mem}[\text{Reg}[R]]$

- Data in register  $R$  specifies the memory address
- Like pointer dereference in C
- Example: `movq (%rcx), %rax`

❖ **Displacement:**  $D (R)$   $\text{Mem}[\text{Reg}[R]+D]$

- Data in register  $R$  specifies the *start* of some memory region
- Constant displacement  $D$  specifies the offset from that address
- Example: `movq 8(%rbp), %rdx`

# Complete Memory Addressing Modes

## ❖ General:

- $D(Rb, Ri, S) \quad \text{Mem}[\text{Reg}[Rb] + \text{Reg}[Ri] * S + D]$ 
  - Rb: Base register (any register)
  - Ri: Index register (any register except `%rsp`)
  - S: Scale factor (1, 2, 4, 8) – *why these numbers?*
  - D: Constant displacement value (a.k.a. immediate)

## ❖ Special cases (see CSPP Figure 3.3 on p.181)

- $D(Rb, Ri) \quad \text{Mem}[\text{Reg}[Rb] + \text{Reg}[Ri] + D] \quad (S=1)$
- $(Rb, Ri, S) \quad \text{Mem}[\text{Reg}[Rb] + \text{Reg}[Ri] * S] \quad (D=0)$
- $(Rb, Ri) \quad \text{Mem}[\text{Reg}[Rb] + \text{Reg}[Ri]] \quad (S=1, D=0)$
- $(, Ri, S) \quad \text{Mem}[\text{Reg}[Ri] * S] \quad (Rb=0, D=0)$

# Address Computation Examples

<code>%rdx</code>	<b><code>0xf000</code></b>
<code>%rcx</code>	<b><code>0x0100</code></b>

$$D(Rb, Ri, S) \rightarrow$$

$$\text{Mem}[\text{Reg}[Rb] + \text{Reg}[Ri] * S + D]$$

Expression	Address Computation	Address
<code>0x8(%rdx)</code>		
<code>(%rdx,%rcx)</code>		
<code>(%rdx,%rcx,4)</code>		
<code>0x80(,%rdx,2)</code>		

# Address Computation Instruction

- ❖ `leaq src, dst`
  - "lea" stands for *load effective address*
  - `src` is address expression (any of the formats we've seen)
  - `dst` is a register
  - Sets `dst` to the *address* computed by the `src` expression (**does not go to memory! – it just does math**)
  - Example: `leaq (%rdx, %rcx, 4), %rax`
- ❖ Uses:
  - Computing addresses without a memory reference
    - e.g. translation of `p = &x[i];`
  - Computing arithmetic expressions of the form  $x+k*i+d$ 
    - Though `k` can only be 1, 2, 4, or 8

# Example: lea vs. mov

## Registers

%rax	
%rbx	
%rcx	0x4
%rdx	0x100
%rdi	
%rsi	

## Memory Word Address

0x400	0x120
0xF	0x118
0x8	0x110
0x10	0x108
0x1	0x100

```
leaq (%rdx,%rcx,4), %rax
movq (%rdx,%rcx,4), %rbx
leaq (%rdx), %rdi
movq (%rdx), %rsi
```

lea – “It just does math”

# Arithmetic Example

```

long arith(long x, long y, long z)
{
    long t1 = x + y;
    long t2 = z + t1;
    long t3 = x + 4;
    long t4 = y * 48;
    long t5 = t3 + t4;
    long rval = t2 * t5;
    return rval;
}

```

```

arith:
    leaq    (%rdi,%rsi), %rax
    addq    %rdx, %rax
    leaq    (%rsi,%rsi,2), %rdx
    salq    $4, %rdx
    leaq    4(%rdi,%rdx), %rcx
    imulq   %rcx, %rax
    ret

```

Register	Use(s)
%rdi	1 <sup>st</sup> argument (x)
%rsi	2 <sup>nd</sup> argument (y)
%rdx	3 <sup>rd</sup> argument (z)

- ❖ Interesting Instructions
  - leaq: “address” computation
  - salq: shift
  - imulq: multiplication
    - Only used once!

# Arithmetic Example

```

long arith(long x, long y, long z)
{
    long t1 = x + y;
    long t2 = z + t1;
    long t3 = x + 4;
    long t4 = y * 48;
    long t5 = t3 + t4;
    long rval = t2 * t5;
    return rval;
}

```

Register	Use(s)
%rdi	x
%rsi	y
%rdx	z, t4
%rax	t1, t2, rval
%rcx	t5

```

arith:
    leaq    (%rdi,%rsi), %rax    # rax/t1    = x + y
    addq   %rdx, %rax           # rax/t2    = t1 + z
    leaq   (%rsi,%rsi,2), %rdx   # rdx       = 3 * y
    salq   $4, %rdx             # rdx/t4    = (3*y) * 16
    leaq   4(%rdi,%rdx), %rcx    # rcx/t5    = x + t4 + 4
    imulq  %rcx, %rax           # rax/rval  = t5 * t2
    ret

```

# Polling Question [Asm II – a]

❖ Which of the following x86-64 instructions correctly calculates `%rax = 9 * %rdi`?

▪ Vote at <http://pollev.com/pbjones>

A. `leaq (,%rdi,9), %rax`

B. `movq (,%rdi,9), %rax`

C. `leaq (%rdi,%rdi,8), %rax`

D. `movq (%rdi,%rdi,8), %rax`

E. We're lost...

# Control Flow

Register	Use(s)
%rdi	1 <sup>st</sup> argument (x)
%rsi	2 <sup>nd</sup> argument (y)
%rax	return value

```
long max(long x, long y)
{
    long max;
    if (x > y) {
        max = x;
    } else {
        max = y;
    }
    return max;
}
```

```
max:
    ???
    movq    %rdi, %rax
    ???
    ???
    movq    %rsi, %rax
    ???
    ret
```

# Control Flow

Register	Use(s)
%rdi	1 <sup>st</sup> argument (x)
%rsi	2 <sup>nd</sup> argument (y)
%rax	return value

```
long max(long x, long y)
{
    long max;
    if (x > y) {
        max = x;
    } else {
        max = y;
    }
    return max;
}
```

**Conditional jump**

**Unconditional jump**

```
max:
    if x <= y then jump to else
    movq    %rdi, %rax
    jump to done
else:
    movq    %rsi, %rax
done:
    ret
```

# Conditionals and Control Flow

- ❖ Conditional branch/*jump*
  - Jump to somewhere else if some *condition* is true, otherwise execute next instruction
- ❖ Unconditional branch/*jump*
  - *Always* jump when you get to this instruction
- ❖ Together, they can implement most control flow constructs in high-level languages:
  - **if** (*condition*) **then** {...} **else** {...}
  - **while** (*condition*) {...}
  - **do** {...} **while** (*condition*)
  - **for** (*initialization*; *condition*; *iterative*) {...}
  - **switch** {...}


# x86 Control Flow

- ❖ **Condition codes**
- ❖ **Conditional and unconditional branches**
- ❖ **Loops**
- ❖ **Switches**


# Processor State (x86-64, partial)

- ❖ Information about currently executing program
  - Temporary data ( `%rax`, ... )
  - Location of runtime stack ( `%rsp` )
  - Location of current code control point ( `%rip`, ... )
  - Status of recent tests ( **CF**, **ZF**, **SF**, **OF** ) "flags"
    - Single bit registers:

## Registers



current top of the Stack



# Condition Codes (Implicit Setting)

- ❖ *Implicitly* set by **arithmetic** operations
  - (think of it as side effects)
  - Example: **addq** src, dst  $\leftrightarrow$  r = d+s
  - **CF=1** if carry out from MSB (*unsigned* overflow)
  - **ZF=1** if r==0
  - **SF=1** if r<0 (if MSB is 1)
  - **OF=1** if *signed* overflow  
(s>0 && d>0 && r<0) || (s<0 && d<0 && r>=0)
  - **Not set by lea instruction (beware!)**



# Condition Codes (Explicit Setting: Compare)

## ❖ Explicitly set by **Compare** instruction

- `cmpq src1, src2`
- `cmpq a, b` sets flags based on  $b-a$ , but doesn't store  $b-a$
- **CF=1** if carry out from MSB (good for *unsigned* comparison)
- **ZF=1** if  $a==b$
- **SF=1** if  $(b-a) < 0$  (if MSB is 1)
- **OF=1** if *signed* overflow  
 $(a > 0 \ \&\& \ b < 0 \ \&\& \ (b-a) > 0) \ ||$   
 $(a < 0 \ \&\& \ b > 0 \ \&\& \ (b-a) < 0)$



# Condition Codes (Explicit Setting: Test)

## ❖ Explicitly set by **Test** instruction

- **testq** src2, src1
- **testq** a, b sets flags based on a&b, but doesn't store a&b
  - Useful to have one of the operands be a *mask*
- Can't have carry out (**CF**) or overflow (**OF**)
- **ZF=1** if a&b==0
- **SF=1** if a&b<0 (signed)



# Using Condition Codes: Jumping

## ❖ $j^*$ Instructions

- Jumps to **target** (an address) based on condition codes

*don't worry about the details*

Instruction	Condition	Description <i>(always compared to 0)</i>
<code>jmp target</code>	1	Unconditional
<code>je target</code>	ZF	Equal / Zero
<code>jne target</code>	$\sim ZF$	Not Equal / Not Zero
<code>js target</code>	SF	Negative
<code>jns target</code>	$\sim SF$	Nonnegative
<code>jg target</code>	$\sim (SF \wedge OF) \ \& \ \sim ZF$	Greater (Signed)
<code>jge target</code>	$\sim (SF \wedge OF)$	Greater or Equal (Signed)
<code>jl target</code>	$(SF \wedge OF)$	Less (Signed)
<code>jle target</code>	$(SF \wedge OF) \   \ ZF$	Less or Equal (Signed)
<code>ja target</code>	$\sim CF \ \& \ \sim ZF$	Above (unsigned ">")
<code>jb target</code>	CF	Below (unsigned "<")

# Using Condition Codes: Setting


## ❖ `set*` Instructions

- Set low-order byte of `dst` to 0 or 1 based on condition codes
- Does not alter remaining 7 bytes

Instruction	Condition	Description
<code>sete dst</code>	ZF	Equal / Zero
<code>setne dst</code>	$\sim$ ZF	Not Equal / Not Zero
<code>sets dst</code>	SF	Negative
<code>setns dst</code>	$\sim$ SF	Nonnegative
<code>setg dst</code>	$\sim (SF \wedge OF) \ \& \ \sim ZF$	Greater (Signed)
<code>setge dst</code>	$\sim (SF \wedge OF)$	Greater or Equal (Signed)
<code>setl dst</code>	$(SF \wedge OF)$	Less (Signed)
<code>setle dst</code>	$(SF \wedge OF) \   \ ZF$	Less or Equal (Signed)
<code>seta dst</code>	$\sim CF \ \& \ \sim ZF$	Above (unsigned ">")
<code>setb dst</code>	CF	Below (unsigned "<")

# Reminder: x86-64 Integer Registers

## ❖ Accessing the low-order byte:



# Reading Condition Codes

Register	Use(s)
%rdi	1 <sup>st</sup> argument (x)
%rsi	2 <sup>nd</sup> argument (y)
%rax	return value

## ❖ set\* Instructions

- Set a low-order byte to 0 or 1 based on condition codes
- Operand is byte register (e.g. al, dl) or a byte in memory
- Do not alter remaining bytes in register
  - Typically use `movzbl` (zero-extended `mov`) to finish job

```
int gt(long x, long y)
{
    return x > y;
}
```

```
cmpq    %rsi, %rdi    #
setg    %al           #
movzbl  %al, %eax     #
ret
```

# Reading Condition Codes

Register	Use(s)
%rdi	1 <sup>st</sup> argument (x)
%rsi	2 <sup>nd</sup> argument (y)
%rax	return value

## ❖ set\* Instructions

- Set a low-order byte to 0 or 1 based on condition codes
- Operand is byte register (e.g. al, dl) or a byte in memory
- Do not alter remaining bytes in register
  - Typically use `movzbl` (zero-extended `mov`) to finish job

```
int gt(long x, long y)
{
    return x > y;
}
```

```
cmpq    %rsi, %rdi    # Compare x:y
setg    %al           # Set when >
movzbl  %al, %eax     # Zero rest of %rax
ret
```

# Aside: movz and movs

`movz __ src, regDest`      # Move with zero extension

`movs __ src, regDest`      # Move with sign extension

- Copy from a *smaller* source value to a *larger* destination
- Source can be memory or register; Destination *must* be a register
- Fill remaining bits of dest with **zero** (`movz`) or **sign bit** (`movs`)


`movzSD` / `movsSD`:

S – size of source (**b** = 1 byte, **w** = 2)

D – size of dest (**w** = 2 bytes, **l** = 4, **q** = 8)

Example:

`movzbq %al, %rbx`



# Aside: movz and movs

`movz __ src, regDest` # Move with zero extension

`movs __ src, regDest` # Move with sign extension

- Copy from a *smaller* source value to a *larger* destination
- Source can be memory or register; Destination *must* be a register
- Fill remaining bits of dest with **zero** (`movz`) or **sign bit** (`movs`)

`movz`*SD* / `movs`*SD*:


*S* – size of source (**b** = 1 byte, **w** = 2)

*D* – size of dest (**w** = 2 bytes, **l** = 4, **q** = 8)

**Note:** In x86-64, any instruction that generates a 32-bit (long word) value for a register also sets the high-order portion of the register to 0. Good example on p. 184 in the textbook.

Example:

`movsbl (%rax), %ebx`



Copy 1 byte from memory into 8-byte register & sign extend it

# Summary

- ❖ **Memory Addressing Modes:** The addresses used for accessing memory in `MOV` (and other) instructions can be computed in several different ways
  - *Base register, index register, scale factor, and displacement* map well to pointer arithmetic operations
- ❖ Control flow in x86 determined by status of Condition Codes
  - Showed **C**arry, **Z**ero, **S**ign, and **O**verflow, though others exist
  - Set flags with arithmetic instructions (implicit) or Compare and Test (explicit)
  - Set instructions read out flag values
  - Jump instructions use flag values to determine next instruction to execute