# Virtual Memory III

CSE 351 Spring 2024

#### **Instructor:**

Elba Garza

#### **Teaching Assistants:**

Ellis Haker
Adithi Raghavan
Aman Mohammed
Brenden Page
Celestine Buendia
Chloe Fong
Claire Wang
Hamsa Shankar


Maggie Jiang Malak Zaki Naama Amiel Nikolas McNamee Shananda Dokka Stephen Ying Will Robertson

virtual memory JULIA EVANS @ bork 17 every program has its physical memory has your computer has own virtual address space addresses, like physical memory 0-8GB {0x 129520 → "puppies" but when your program references an address like 0x 5c69a2a2, 00 {0x 129520 - "bananas 8GB ZOL-PIN SODIMM DOR3 CE & that's not a physical memory address! It's a virtual address. every time you switch inux keeps a mapping from when your program which process is running, virtual memory pages to accesses a virtual address physical memory pages called Linux needs to switch I'm accessing the page table the page table 0x21000 a "page" is a 4kb sometimes chunk of memory bigger here's the address of I'll look that up in process 2950's page table the page table and Linux then access the right } MMU virtual addr physical addr physical address thanks, I'll use memory management 1971 0x 20000 0×192000 that now ! Ox 22 8 000 0x 20000 0x21000 0x 9788000 hardware

Playlist: CSE 351 24Sp Lecture Tunes!

#### **Announcements, Reminders**

- Whirlwind week recap & effects
  - Lab 3 & Midterm grades by tonight
  - LC 21 & 22 inked slides coming soon
  - Possible changes still forthcoming!
- HW22 due tonight
  - HW23 due Wednesday (22 May)
  - HW 24/25 due Friday (24 May)
- Lab 4 due tonight by 11:59 PM! Lab 5 due May 31st
- Memory Day holiday next Monday (27 May)
- Final Exam: June 3<sup>rd</sup> through June 5<sup>th</sup>, on Gradescope. More to come!



#### **Reading Review**

- Terminology:
  - Address translation: page hit, page fault
  - Translation Lookaside Buffer (TLB): TLB Hit, TLB Miss

# But first, some history... (1966)



Systems Reference Library

#### IBM System/360 Model 67

#### **Functional Characteristics**

This publication contains detailed information on the organization, characteristics, features, and functions unique to the IBM System/360 Model 67 Time Sharing System. Major areas described include time-sharing philosophy, system structure, new units, generalized information flow, standard and special features, instruction timings, and the system control panel.

Descriptions of specific input/output devices used with the Model 67 appear in separate publications. See the *IBM System/360 Bibliography*, Form GA22-6822 for a listing and a brief description of these publications.

The material in this publication is presented with the assumption that the reader has knowledge of System/360 as defined in the *IBM System/360 Principles of Operation*, Form GA22-6821 and the *IBM System/360 System Summary*, Form GA22-6810. The *IBM System/360 Model 67 Configurator*, Form GA27-2713 also may be of interest to the reader.

# But first, some history... (1966)

command system.

#### **Paging**

Every program using the system is treated as a sequence of 4096-byte units called "pages". By dividing programs into pages, processor storage can be allocated in page (4096-byte) increments. Program pages, therefore, can be located randomly throughout core storage and swapped in and out of processor storage, as pages are needed, commensurate with available space. Random location of pages for a given program necessitates the construction of tables (page tables) that reflect the processor storage location of the pages. The swapping of pages between auxiliary storage and processor storage is defined as "page turning". If a page of instructions refers to a program location not currently in processor storage, the system stops operating the program temporarily, makes arrangements to fetch the page from auxiliary storage (the disk and drum storage space reserved specifically for paging), and performs other operations in the interim.

System Description 7


"Page turning" has the following advantages:

- The entire program need not be in core storage to operate. Parts of many programs can be present, and several may be ready for processing. Thus, the system has many opportunities to do useful work while a page is being swapped.
- 2. Program "swap time" is reduced as an overhead factor since only active pages of a program require movement between core storage and auxiliary storage.
- 3. Although written and executed as a classical set of contiguous instructions and working space, a program can exist in the machine as scattered active pages.

The programmer's concept of the program being executed is of a "virtual storage" rather than of an actual processor storage situation.


The user's virtual storage is the contiguous address space that would be needed to store the user's program. This virtual storage is not limited by actual processor storage size but is limited only by the available auxiliary (disk and drum) space. Theoretically, the programmer has 16 million bytes (24-bit addressing) or up to 4 billion bytes (optional 32-bit addressing) of virtual storage at his disposal.

#### Taking A Step Back: Address Translation Page Hit



- 1) Processor sends virtual address to MMU (memory management unit)
- **2-3)** MMU fetches PTE from page table in cache/memory; valid bit is <u>one</u> (Uses PTBR to find beginning of page table for current process)
- 4) MMU sends physical address to cache/memory requesting data
- 5) Cache/memory sends data to processor

## Taking a Step Back: Address Translation Page Fault



- 1) Processor sends virtual address to MMU
- 2-3) MMU fetches PTE from page table in cache/memory
- 4) Valid bit is zero, so MMU triggers page fault exception & thus page fault handler
- 5) Handler identifies victim (and, if dirty, pages it out to disk)
- 6) Handler pages in new page and updates PTE in memory
- 7) Handler returns to original process, restarting faulting instruction

#### Hmm... Translation Sounds Slow...

- The MMU accesses memory twice: once to get the PTE for translation, and then again for the actual memory request
  - The PTEs may be cached in L1 like any other memory word
    - But they may be evicted by other data references
    - And a hit in the L1 cache still requires 1-3 cycles

What can we do to make this faster?


**Solution:** add another cache!




#### **Speeding up Translation with a TLB**


#### Translation Lookaside Buffer (TLB):

- Stores page table entries for a small number of pages
  - Modern Intel processors have 128 or 256 entries in TLB
- Small hardware cache in MMU
  - Split VPN into TLB Tag and TLB Index based on # of sets in TLB
- Maps virtual page numbers to physical page numbers
- Much faster than a page table lookup in cache/memory
- How to compute TLB index? Split the VPN!





A TLB hit eliminates a memory access!




- A TLB miss incurs an additional memory access (the PTE)
  - Fortunately, TLB misses are rare

## **Textual Equivalent: Fetching Data on a Memory Read**


- 1) Address Translation (check TLB)
  - Input: VPN from Virtual Address (VA), Output: PPN for Physical Address (PA)
  - TLB Hit: Fetch translation, return PPN, DONE!
  - TLB Miss: Check page table (in memory)
    - Page Table Hit: Load page table entry into TLB, return PPN, DONE!
    - Page Fault: Fetch page from disk to memory, update corresponding page table entry, then load entry into TLB, then return PPN, DONE!
- 2) Now with PA... Fetch Data (check cache)
  - Input: Physical Address (PA), Output: data
  - Cache Hit: Return data value to processor, DONE!
  - Cache Miss: Fetch data value from memory, store it in cache, return it to processor, DONE!

#### Flow Chart Equivalent: Address Translation

**NOTE:** If the line looks thicker, that means that path takes longer time...



## **Address Manipulation**



#### **Context Switching Revisited**

- What needs to happen when the CPU switches processes?
  - Registers:
    - Save state of old process, load state of new process
    - Including the Page Table Base Register (PTBR)
  - Memory:
    - Nothing to do! Pages for processes already exist in memory/disk and protected from each other
  - TLB:
    - Invalidate all entries in TLB—mapping is for old process' VAs!
    - Yep, have to start with a cold TLB
  - Cache:
    - Can leave alone because storing based on PAs—good for shared data


#### **Summary of Address Translation Symbols**

- Basic Parameters
  - $N = 2^n$  Number of addresses in virtual address space
  - $M = 2^m$  Number of addresses in physical address space
  - $P = 2^p$  Page size (bytes)
- Components of the virtual address (VA)
  - VPO Virtual page offset
  - VPN Virtual page number
  - **TLBI** TLB index
  - **TLBT** TLB tag
- Components of the physical address (PA)
  - PPO Physical page offset (same as VPO)
  - PPN Physical page number

# And now let's put it all together...

## **Simple Memory System Example**

\* Addressing: 14-bit virtual addresses (n) & 12-bit physical address (m)



## **Simple Memory System: Page Table**

- Only showing first 16 entries (out of \_\_\_\_\_)
  - Size of page table is  $2^{n-p}$  entries, remember!
  - Note: showing 2 hex digits for PPN even though only 6 bits
  - Note: other management bits not shown, but part of PTE


VPN	PPN	Valid
0	28	1
1	_	0
2	33	1
3	02	1
4	ı	0
5	16	1
6	1	0
7	_	0

VPN	PPN	Valid
8	13	1
9	17	1
Α	09	1
В	-	0
C	_	0
D	2D	1
E	_	0
F	0D	1

16 entries total

4-way set associative

Why does the TLB ignore the page offset? It's not its job to care!



	Way 0		Way 1		Way 2			Way 3				
Set	Tag	PPN	Valid	Tag	PPN	Valid	Tag	PPN	Valid	Tag	PPN	Valid
0	03	_	0	09	0D	1	00	_	0	07	02	1
1	03	2D	1	02	_	0	04	_	0	0A	_	0
2	02	_	0	80	_	0	06	_	0	03	_	0
3	07	_	0	03	0D	1	0A	34	1	02	_	0

CSE351, Spring 2024


# Note: It is just coincidence that the PPN is the same width

as the cache Tag

CSE351, Spring 2024

## **Simple Memory System: Cache**

- Direct-mapped, with K = 4 B, C/K = 16
- Physically addressed



Index	Tag	Valid	<i>B0</i>	B1	<b>B2</b>	<i>B3</i>
0	19	1	99	11	23	11
1	15	0	_	_	_	_
2	1B	1	00	02	04	08
3	36	0	_	_	_	_
4	32	1	43	6D	8F	09
5	0D	1	36	72	F0	1D
6	31	0	_	_	_	_
7	16	1	11	C2	DF	03

Index	Tag	Valid	<i>B0</i>	B1	B2	В3
8	24	1	3A	00	51	89
9	2D	0	_	-	_	_
Α	2D	1	93	15	DA	3B
В	0B	0	_	-	_	_
С	12	0	_	-	_	_
D	16	1	04	96	34	15
Ε	13	1	83	77	1B	D3
F	14	0	_	_	_	_

# **Current State of Memory System**

#### TLB:

Set	Tag	PPN	V									
0	03	_	0	09	0D	1	00	_	0	07	02	1
1	03	2D	1	02	_	0	04	_	0	0A	_	0
2	02	_	0	08	_	0	06	_	0	03	_	0
3	07	_	0	03	0D	1	0A	34	1	02	_	0

#### Page table (partial):

VPN	PPN	V	VPN	PPN	V
0	28	1	8	13	1
1	-	0	9	17	1
2	33	1	A	09	1
3	02	1	В	_	0
4	_	0	С	_	0
5	16	1	D	2D	1
6	_	0	Е	_	0
7	_	0	F	0D	1

#### Cache:


Index	Tag	V	<i>B0</i>	B1	B2	<i>B3</i>
0	19	1	99	11	23	11
1	15	0	-	-	-	_
2	1B	1	00	02	04	08
3	36	0	-	-	-	_
4	32	1	43	6D	8F	09
5	0D	1	36	72	F0	1D
6	31	0	-	-	-	_
7	16	1	11	C2	DF	03


Index	Tag	V	<i>B0</i>	<b>B1</b>	<i>B</i> 2	<i>B3</i>
8	24	1	3A	00	51	89
9	2D	0	-	-	_	_
Α	2D	1	93	15	DA	3B
В	OB	0	-	-	_	_
С	12	0	-	-	_	_
D	16	1	04	96	34	15
Ε	13	1	83	77	1B	D3
F	14	0	_	_	_	_

## **Memory Request Example #1**

Note: It is just coincidence that the PPN is the same width as the cache Tag

❖ Virtual Address: 0x03D4







## **Memory Request Example #2**

coincidence that the PPN is the same width as the cache Tag

Note: It is just

❖ Virtual Address: 0x038F





Note: It is just


coincidence that the PPN is the same width

as the cache Tag

## **Memory Request Example #3**

❖ Virtual Address: 0x0020

TLBT — TLBI — Page Fault? — PPN — TLBI — TLBI — TLBI — Page Fault? — PPN — TLBI — TLBI





# **Memory Request Example #4**

<u>coincidence</u> that the PPN is the same width as the cache Tag


Note: It is just

❖ Virtual Address: 0x036B





#### **Memory Overview (Data Flow)**



## **Virtual Memory Summary**


- Programmer's view of virtual memory
  - Each process has its own private linear address space
  - Cannot be corrupted by other processes

- System view of virtual memory
  - Uses memory efficiently by caching virtual memory pages
    - Efficient only because of locality
  - Simplifies memory management and sharing
  - Simplifies protection by providing permissions checking

# BONUS SLIDES

Multi-level Page Tables


## **Page Table Reality**




- Just one issue... the numbers don't work out for the story so far!
- The problem is the page table for each process:
  - Suppose 64-bit VAs, 8 KiB pages, 8 GiB physical memory
  - How many page table entries is that?
  - About how long is each PTE?

■ Moral: Cannot use this naïve implementation of the virtual → physical page mapping – it's way too big

## A Solution: Multi-level Page Tables





#### **Multi-level Page Tables**

This is extra (non-testable) material

- \* A tree of depth k where each node at depth i has up to  $2^j$  children if part i of the VPN has j bits
- Hardware for multi-level page tables inherently more complicated
  - But it's a necessary complexity 1-level does not fit
- Why it works: Most subtrees are not used at all, so they are never created and definitely aren't in physical memory
  - Parts created can be evicted from cache/memory when not being used
  - Each node can have a size of ~1-100KB
- \* But now for a k-level page table, a TLB miss requires k+1 cache/memory accesses
  - Fine so long as TLB misses are rare motivates larger TLBs